

# Welcome to GSnap

GSnap is an auto-tune effect. It can be used subtly to correct the pitch of a vocal, or, with more extreme settings, to create a robot-voice effect. It requires a monophonic input signal to operate.

## Hints

- Try GSnap with non-vocal material for interesting effects.
- GSnap's effect is more useful with simple material. Complex material with rapid note changes may require several hours of dedicated MIDI programming to deal with, and may still end up sounding less than realistic.
- Use the automatic correction with Forced Key to help approximate that famous vocal effect.
- Automate switching between Fixed and MIDI mode for ultimate control: allow GSnap to do its thing automatically for much of the material, and then "take over" for passages or notes that need specific work.
- Try feeding GSnap some MIDI information in real-time during a vocal passage. You may find the results even more interesting than that "other" vocal effect!

## Interface



The GUI features a set of 12 knobs which control all of the plug-in's parameters. Each has its function clearly labelled above, and features a user-editable readout below. Additionally, twelve "switches" next to the pitch data view correspond to the twelve semitones of a full octave in the Western chromatic scale, and are used to supplement the "fixed" mode of GSnap. Two further switches allow the user to select between "fixed" or "midi" modes, explained below.

The controls are divided into three groups: Detection, Correction, and MIDI. The Detection section allows you to fine-tune GSnap's ability to deal with incoming audio. Correction determines the method and audible effect of the tuning algorithm. MIDI controls determine how GSnap deals with particular MIDI information.

To the left of the controls is a visual representation of the pitch of the source and "tuned" material. The source material appears as a red line graph, and the tuned material a green one. This can help the user zero in on problem notes, and also provide a secondary way (the primary being your ears!) with which to gauge GSnap's effect on the source material.

## Detection Controls

The incoming audio is first processed by this set of controls, which help give GSnap a bit of a break by narrowing down the range of frequencies and sounds that the plug-in has to deal with.

**Min Freq:** Allows the user to set the minimum frequency, in Hertz, that GSnap will consider for correction. The vast majority of human voices will never go below 300 Hz.

**Max Freq:** This allows the user to set the highest frequency that will be considered for tuning. While the harmonics of the human voice can go above 3500 Hz, the fundamentals are generally below 1000 Hz, and are more commonly even below 800.


**Gate:** Any source material at a level below this setting is not considered for tuning. You should set this so that GSnap ignores background noise.

**Speed:** The Speed parameter sets the number of wave repetitions required for pitch-detection. Lower values for Speed will allow faster pitch-detection but increase the chance of false detection, resulting in sporadic jumps in the audio's pitch. The default value should be fine in most cases.

## Correction Controls

Once a pitch has been determined, GSnap applies the specified pitch-correction. There are two modes of pitch correction: fixed scale and MIDI. Fixed scale correction has a fixed set of snap-notes, while MIDI correction is controlled in real time by MIDI data.

**Fixed Mode:** When this mode is selected, notes are "snapped" to a key of the user's choosing. Pressing the "Select Scale..." button located beside the "Fixed Mode" button brings up a dialog box:



A drop-down menu allows you to select the "root" of the scale, and another the "mode". Checking the "Set Threshold..." option will automatically adjust the Threshold parameter so that the chosen scale is enforced.

Once a scale is selected (or at any point in time with "Fixed" mode enabled), the user may add or remove notes from snap. All enabled notes in the scale are highlighted with light blue in small boxes on the "piano keys" next to the graphical display. Disabled notes are indicated with dark blue.

**Midi Mode:** When this option is selected, notes will snap to the nearest currently depressed MIDI note, sent either by a controller being played in real-time, or by a pre-programmed MIDI sequence. For this to work, your sequencer must be set up so that GSnap can receive both audio and MIDI messages.

**Threshold:** Defines the snapping region around each snap-note. A "cent" is a percentage

of a Western semitone. For every 100 cents in the threshold, you add another semitone to the snapping region. A higher threshold allows GSnap to enforce wider "gaps" between notes in customized scales. For standard scales, 100 cents will allow for perfect snapping. With pentatonic scales, 150 cents are necessary.

**Amount:** Sets the amount of correction that will be applied.

**Attack and Release:** These parameters set how quickly a note reaches full correction and subsequently returns to no correction. As a general rule, an extremely fast attack will produce a noticeable and distinctly artificial "snap", but may be necessary to deal with certain phrases. Longer attack and release times can produce a more natural sound, but setting the times too long can also sound unnatural or be ineffective, so exercise caution.

## MIDI Controls

When the user has selected "Midi" mode, these controls are used to set how GSnap will respond to incoming MIDI information.

**Pitch Bend:** Allows the user to set the maximum pitch bend. Since every 100 cents represent a Western-scale semitone, the maximum bend at 200 cents is one full tone.

**Vibrato:** Defines the maximum range of the vibrato applied by manipulating the modulation wheel or sending a mod wheel Continuous Controller (CC) message in a MIDI program. Like Pitch Bend, its maximum range is 200 cents or one full tone.

**Speed:** Represents the speed (in Hertz) of vibrato applied by MIDI when the user uses the modulation wheel or sends a modulation CC.

**Calibrate:** This control allows the user to calibrate the actual "tuning" of GSnap as it relates to the source material, with the number representing the frequency of the note "A" in your song. This setting affects the detected note and consequently the amount of correction.

The default of A=440 Hz is the standard tuning calibration, and should be fine for the majority of situations. However, there are many exceptions, such as when singing to a track with a fixed instrument (i.e. a pipe organ) that is tuned to A=435.

## License

1. GVST plug-ins are provided to the user at no cost. While every GVST plug-in is tested to the best of the developer's ability, no warranty or guarantee is offered to the end user.
2. No suggestions made by the developer or his representatives (i.e., freely offered support) are to be taken as an implied warranty or guarantee.
3. These plug-ins may only be distributed by the official GVST website, or by parties explicitly given permission by the developer.
4. GVST plug-ins are to be distributed only in their original form as intended by the developer (i.e., the unaltered archive).
5. GVST plug-ins are freeware, meaning you are never under any obligation to pay for them! However, should you wish to help support continued development of GVST software, please consider donating through the official website.

## Credits

- Development, code, website and graphics by Graham Yeadon.

- Documentation by Greg Pettit and Graham Yeadon (many thanks to Greg for all of his help).
- VST technology copyright Steinberg GmbH.
- The "VST" name and logo are registered trademarks of Steinberg GmbH.

Copyright Graham Yeadon

I would not make these plug-ins available if I did not feel that they were safe and stable. However, I cannot take responsibility for any damage, difficulty, or stress caused by their use. Please do not download any software unless you agree with the license conditions. VST and Windows are trademarks of Steinberg and Microsoft respectively.